#### **Materials Needed**

## Worsted weight yarn

You'll need two colors: Color A (contrast) and Main Color (MC). Feel free to get creative with your palette! Neutral tones create a modern look, while bright colors add a fun twist.

- Crochet Hook: Size 5 mm (U.S. H/8) or the size needed to obtain gauge.
- Scissors
- Yarn Needle (for weaving in ends)

### **Finished Measurements**

Approx. **51 x 62 inches** (129.5 x 157.5 cm) – the perfect throw blanket for your couch, reading chair, or bed.

### Gauge

13 stitches and 10 rows = 4 inches (10 cm) in pattern.

Tip: Always check your gauge to ensure your blanket comes out the intended size.

#### **Arrow Stitch Blanket Instructions**

### **Foundation**

• With Color A, chain 201.

### Row 1 (Right Side):

- 1 single crochet (sc) in 2nd chain from the hook.
- 1 sc in each chain to the end.
- Chain 1, turn. (200 stitches total)

### **Row 2:**

- 1 sc in each stitch across.
- Join Main Color (MC) at the end of the row.
- Chain 3, turn.

## **Row 3:**

- Skip the first stitch.
- 1 double crochet (dc) in the next stitch.
- Skip the next 3 stitches.

- 1 treble crochet (tr) in the next stitch.
- Working **behind** the treble crochet just made, 1 dc in the first missed stitch, then 1 dc in each of the next 2 missed stitches.

### Repeat pattern:

- \*Skip next 3 stitches after the treble crochet.
- 1 tr in the next stitch.
- Working behind the tr, 1 dc in the first missed stitch, then 1 dc in each of the next 2 missed stitches.\*

Repeat from \* to the last 2 stitches.

- 1 dc in each of the last 2 stitches.
- Chain 3, turn.

### **Row 4:**

- Skip the first stitch.
- 1 dc in the next dc.
- Skip next 3 dc.
- 1 tr in the next tr.
- Working **in front** of the tr just made, 1 dc in the first missed dc, then 1 dc in each of the next 2 missed dc.

## Repeat pattern:

- \*Skip next 3 dc after the tr.
- 1 tr in the next tr.
- Working in front of the tr, 1 dc in the first missed dc, then 1 dc in each of the next 2 missed dc.\*

Repeat from \* to the last 2 stitches.

- 1 dc in each of the last 2 stitches.
- Join Color A.
- Chain 1, turn.

### **Row 5:**

• 1 sc in each stitch across.

• Chain 1, turn.

# **Pattern Repeat**

Rows 2 to 5 form the pattern.

Continue in this sequence until your blanket measures approximately **50 inches** (127 cm), ending with a **Row 2** (single crochet row).

Do not chain at the end of the last row.

Fasten off.

# **Edging**

- Join Main Color to any corner of the blanket.
- Work 1 row of single crochet (sc) evenly around the entire outer edge, making 3 sc in each corner.
- Join with a slip stitch (ss) to the first sc.

### **Final Round:**

- Work reverse single crochet (crab stitch) around the entire blanket.
  (This is worked from left to right instead of the usual right to left, creating a neat, corded edge.)
- Slip stitch to the first sc and fasten off.